

Introduction

The Health Thermometer Profile is used to enable a data collection device to obtain data from a thermometer sensor that exposes the Health Thermometer Service.

The profile defines two roles:

- **Thermometer:**
The Thermometer is the device that measures the temperature.
- **Collector:**
The Collector is the device that receives the temperature measurement and other data from a thermometer.

Features

- Device Discovery and Disconnection
- Pairing/Bonding
- RSSI Sampling
- Health Thermometer Service
- Health Thermometer Profile iOS/Android Application

Table of Contents

1	Purpose	3
2	Services and Characteristics	3
3	Demo Setup.....	3
4	Hardware Setup	3
5	Temperature Measurement Location.....	4
6	Temperature Type.....	4
7	Software Setup.....	5
	7.1 Installation Steps	5
	7.2 Build Procedure.....	5
8	Console Logging	7
9	Running the Demo	7
10	BluSDK SMART Software Architecture	10
11	ATMEL EVALUATION BOARD/KIT IMPORTANT NOTICE AND DISCLAIMER	11
12	Revision History	12

1 Purpose

This getting started guide describes the setup of an Atmel® ATSAMB11 Xplained board and bringing up an example profile supplied as part of BluSDK SMART release. The Bluetooth® Health Thermometer Profile is an example profile application that is embedded as part of the software release package. The device advertises itself as a Health Thermometer. The ATSAMB11 Xplained board includes an on-board temperature sensor (accessible from the host MCU) for the purpose of sensing the ambient temperature.

2 Services and Characteristics

The thermometer implements the one and only one Health Thermometer Service in addition to the Device Information Service to display the information about the thermometer device.

The current thermometer profile implementation implements the following characteristics:

- Temperature Measurement
- Intermediate Temperature
- Measurement Interval


3 Demo Setup



4 Hardware Setup

Connect the ATSAMB11 board to the host PC using a Micro-USB cable.

Figure 4-1. EDBG USB Port



5 Temperature Measurement Location

Onboard the ATSAMB11, the user button is configured to change the temperature measurement location in the human body.

The Health Thermometer profile specifies the following locations at which temperature measurements can be read:

- Body (general)
- Ear (usually ear lobe)
- Finger
- Gastro-intestinal Tract
- Mouth
- Rectum
- Toe
- Tympanum (ear drum)

In order to simulate the change of temperature measurement location from the Thermometer Sensor device, the user button is preprogrammed; Every time the user button is pressed, the temperature location will be changed as per the above list.

This can clearly be observed on a Health Thermometer Collector (Mobile Application).

6 Temperature Type

One more parameter that needs to be simulated is the temperature measurement type which contains two units of measurement; Centigrade and Fahrenheit.

To simulate this change on the peripheral side, as there is only one user button available on board which had already been used for changing the temperature location, the trigger that is used for this is to run through all the locations once. Then the application shall toggle the temperature type.

7 Software Setup

7.1 Installation Steps

1. Install the latest Atmel Studio [Atmel Studio 7.0 (build 629 or later) web installer (recommended)]
<http://www.atmel.com/tools/ATMELSTUDIO.aspx>.

2. Install the latest Atmel Software Framework.

This package will install the following examples within the Atmel Studio environment:


- Health Thermometer Application for ATSAMB11

7.2 Build Procedure

The following procedure is explained for ATSAMB11 application example.


1. Select New Example Project.

Figure 7-1. Creating a New Example Project




2. Select "SAMB11" in device family, enter "HTP" in the search window, and expand Atmel Corp Projects. The location and the name of the project can be selected in the respective fields. Click OK.

Figure 7-2. Selecting Scan Parameter Service Application from Example Projects




3. Accept the license Agreement. The studio will generate the Health Thermometer Profile project for ATSAMB11.
4. Build the solution.

Figure 7-3. Building the HTPPT Temperature Sensor Application




5. Download the application via the USB to the ATSAMB11 board.

Figure 7-4. Flashing the Application on Atmel MCU



6. Inside the device programming the user has to select the correct configuration for the device and finally program the device by using the program button.

Figure 7-5. Flash Programming



7. Once the application is flashed, it is ready to be simulated as Health Thermometer Device.

8 Console Logging

For the purpose of debugging, a logging interface has been implemented in the Health Thermometer Application.

The logging interface utilizes the same EDBG port that connects to ATSAMB11. A serial port monitor application (for example TeraTerm) shall be opened and attached to the EDBG COM port.

9 Running the Demo


1. Power on the ATSAMB11 by connecting the USB cable.
2. Open the console using TeraTerm or any serial port monitor application and connect to the corresponding COM port of “EDBG”. Serial port settings: Baudrate 115200, None Parity, one Stop bit, one Start bit, no Hardware Handshake.
3. Press the Reset button on the ATSAMB11 board.
4. The board should be in advertising mode. Ensure that the console log looks as shown below.

Figure 9-1. Console Log for Advertising Mode

```
App_entry =====  
AT_BLE_HTPT_CREATE_DB_CFM / 0  
Please fine ATMEL-B11-HTP device
```


5. Start the Thermometer application on the iPhone/Android.

Figure 9-2. iOS(left)/Android(right) Thermometer Profile App Launch Screen



6. Enable the scan option through the sliding switch. The application is implemented in such a way that it filters out all the other UUID's and connects to only those peripherals that advertise with Health Thermometer UUID (0x1809).

Figure 9-3. iOS(Left-1-image)/Android(Right-2-images) App Health Thermometer Initial Screen



7. The temperature value, RSSI, and the device name are all displayed on the Mobile App. Console log will be as shown below.

Figure 9-4. iOS(Left)/Android(Right-2-images) App Health Thermometer Connected Screen





Figure 9-5. Console Log for Connected State

```
app_entry =====
AT_BLE_HTPPT_CREATE_DB_CFM / 0
Please find ATMEL-B11-HTP device
AT_BLE_CONNECTED / 2, 0x43, 0x15, 0xdb, 0x9c, 0xd0, 0x53, 0, 0
AT_BLE_PAIR_REQUEST /
AT_BLE_PAIR_DONE /
AT_BLE_HTPPT_CFG_INDNTF_IND / 0, 2, 0
AT_BLE_HTPPT_CFG_INDNTF_IND / measurement_interval 5
AT_BLE_HTPPT_CFG_INDNTF_IND / 0, 1, 2
htpt_temperature_send / at_ble_htpt_temp_send / 28.062500
HTPT_TEMP_SEND_CFM / 0, 0, cfm_type 1
htpt_temperature_send / at_ble_htpt_temp_send / 28.062500
HTPT_TEMP_SEND_CFM / 0, 0, cfm_type 1
```

8. To change the body measurement location, press the user button on the ATSAMB11. The new value should be updated in the application.

Figure 9-6. The User Button




9. In the iOS app, pull the slider to disconnect the device with mobile application. On the Atmel SmartBLU Android application, going back to the scanning screen will disconnect the device with mobile application.

10 BluSDK SMART Software Architecture

Figure 10-1 illustrates the top level diagram for the ATSAMB11 configuration.

Figure 10-1. ATSAMB11 Software Architecture



11 **ATMEL EVALUATION BOARD/KIT IMPORTANT NOTICE AND DISCLAIMER**

This evaluation board/kit is intended for user's internal development and evaluation purposes only. It is not a finished product and may not comply with technical or legal requirements that are applicable to finished products, including, without limitation, directives or regulations relating to electromagnetic compatibility, recycling (WEEE), FCC, CE or UL. Atmel is providing this evaluation board/kit "AS IS" without any warranties or indemnities. The user assumes all responsibility and liability for handling and use of the evaluation board/kit including, without limitation, the responsibility to take any and all appropriate precautions with regard to electrostatic discharge and other technical issues. User indemnifies Atmel from any claim arising from user's handling or use of this evaluation board/kit. Except for the limited purpose of internal development and evaluation as specified above, no license, express or implied, by estoppel or otherwise, to any Atmel intellectual property right is granted hereunder. ATMEL SHALL NOT BE LIABLE FOR ANY INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES RELATING TO USE OF THIS EVALUATION BOARD/KIT.

ATMEL CORPORATION
1600 Technology Drive
San Jose, CA 95110
USA

12 Revision History

Doc Rev.	Date	Comments
42601A	11/2015	Initial document release.



Atmel Corporation 1600 Technology Drive, San Jose, CA 95110 USA T: (+1)(408) 441.0311 F: (+1)(408) 436.4200 | www.atmel.com

© 2015 Atmel Corporation. / Rev.: Atmel-42601A-ATSAMB11-BluSDK-SMART-Health-Thermometer-Profile-Getting-Started-Guide_UserGuide_112015.

Atmel®, Atmel logo and combinations thereof, Enabling Unlimited Possibilities®, and others are registered trademarks or trademarks of Atmel Corporation in U.S. and other countries. ARM®, ARM Connected® logo, and others are the registered trademarks or trademarks of ARM Ltd. Other terms and product names may be trademarks of others.

DISCLAIMER: The information in this document is provided in connection with Atmel products. No license, express or implied, by estoppel or otherwise, to any intellectual property right is granted by this document or in connection with the sale of Atmel products. EXCEPT AS SET FORTH IN THE ATMEL TERMS AND CONDITIONS OF SALES LOCATED ON THE ATMEL WEBSITE, ATMEL ASSUMES NO LIABILITY WHATSOEVER AND DISCLAIMS ANY EXPRESS, IMPLIED OR STATUTORY WARRANTY RELATING TO ITS PRODUCTS INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. IN NO EVENT SHALL ATMEL BE LIABLE FOR ANY DIRECT, INDIRECT, CONSEQUENTIAL, PUNITIVE, SPECIAL OR INCIDENTAL DAMAGES (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS AND PROFITS, BUSINESS INTERRUPTION, OR LOSS OF INFORMATION) ARISING OUT OF THE USE OR INABILITY TO USE THIS DOCUMENT, EVEN IF ATMEL HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. Atmel makes no representations or warranties with respect to the accuracy or completeness of the contents of this document and reserves the right to make changes to specifications and products descriptions at any time without notice. Atmel does not make any commitment to update the information contained herein. Unless specifically provided otherwise, Atmel products are not suitable for, and shall not be used in, automotive applications. Atmel products are not intended, authorized, or warranted for use as components in applications intended to support or sustain life.

SAFETY-CRITICAL, MILITARY, AND AUTOMOTIVE APPLICATIONS DISCLAIMER: Atmel products are not designed for and will not be used in connection with any applications where the failure of such products would reasonably be expected to result in significant personal injury or death ("Safety-Critical Applications") without an Atmel officer's specific written consent. Safety-Critical Applications include, without limitation, life support devices and systems, equipment or systems for the operation of nuclear facilities and weapons systems. Atmel products are not designed nor intended for use in military or aerospace applications or environments unless specifically designated by Atmel as military-grade. Atmel products are not designed nor intended for use in automotive applications unless specifically designated by Atmel as automotive-grade.